



WINDOWS 7 USB CARD DIALUP CONNECTION


It's possible to bypass the connection manager and setup a dialup connection. The appropriate drivers must be loaded prior to execution of these procedures.



1. Install and start the connection manager
2. Insert the data card
3. Select the Setting tab
3. Select (M)



3. If you have installed the drivers properly you will see the data card and phone number listed.
4. Make sure the box is checked and highlight the card.
5. Select the APN (A) button on the top right



6. A popup box will appear. Select OK.



7. We're looking for the APN :
mopera.flat.foma.ne.jp

Normally, it's listed as either the 2nd, 3rd or 4th address. Note the location and close the connection manager.

Now, when setting up the standard dialup connection you will use the following dialup number: *99***2#. Use *99***4# if the location on the list was in the 4th position.

You should be able to connect via you dialup connection and may be able to use the connection manager after making these changes.